

Welcome to Fedora Discussion!



Check out our [guide to navigation: tags, categories, and concepts](#), or add to our [tips and tricks](#).

GNOME suspends after 15 minutes of user inactivity, even on AC power

#gnome #f38 #workstation #f39 #suspend-resume

Kamil Páral  **kparal** Proven Tester

Nov 2

Problem

Since Fedora 38, systems with the GNOME desktop environment suspend after 15 minutes of user inactivity, even when plugged in to the AC outlet. This affects new installs and some upgraded systems (depending whether you touched that setting in the past).


This is due to an intentional change. To give it a better visibility, and because it might surprise many users and consider it a bug, it's documented here.


Note: Remote sessions might not be considered when GNOME tracks user activity. Graphical remote sessions might count as user active, but that depends on the session server. An SSH session is not counted towards user activity.

Note: *Fedora Server* ships a configuration override, which defaults to not suspending on AC power by default. In all other Fedora editions, the described configuration change should apply, as long as you have GNOME environment running.

Solution

You can check and configure your current behavior in *Settings → Power → Automatic Suspend*:





Please note that these settings are your personal configuration only. Each user can configure their own settings. And, most importantly, changes to these settings don't apply to the login screen. If you're at the login screen (e.g. after a system boot or a user logout), the default options are used (15 minutes timeout).

Adjusting the login screen

If you want to modify the login screen behavior, you can display the current login screen settings with this command:

```
sudo -u gdm dbus-run-session gsettings list-recursively org.gnome.set...
```

Which prints an output like this:

```
org.gnome.settings-daemon.plugins.power sleep-inactive-ac-timeout 900
org.gnome.settings-daemon.plugins.power sleep-inactive-ac-type 'suspen'
org.gnome.settings-daemon.plugins.power sleep-inactive-battery-timeou...
org.gnome.settings-daemon.plugins.power sleep-inactive-battery-type '...
```

The `sleep-inactive-ac-timeout` is the *Plugged in* option and `sleep-inactive-battery-timeout` is the *On Battery Power* option. The number is the delay in seconds. You can configure the values like this:

```
sudo -u gdm dbus-run-session gsettings set org.gnome.settings-daemon.|
```

This sets the *Plugged in* delay to `1800` seconds, i.e. 30 minutes. You can use `0` to disable the automatic suspend completely. You can verify that the option was set by displaying the current values as described above.

Cause

This is to satisfy energy certifications. Automatic suspend when plugged in was enabled for a long time in GNOME already, but there was a local patch in Fedora that used to disable it. Since Fedora 38, that override is removed (except for *Fedora Server*).

Related Issues

https://bugzilla.redhat.com/show_bug.cgi?id=1823420

<https://pagure.io/fedora-workstation/issue/501>

You can discuss this topic [here](#).

Talk: GNOME suspends after 15 minutes of user inactivity, even on AC power

System Suspends

Fedora 38 Silverblue suspends even though Power settings disallow it

Presentation mode on fedora 38 gnome

Restart instead Shutdown

[3 more](#)

Related Topics

Topic	Replies	Views	Activity
Talk: GNOME suspends after 15 minutes of user inactivity, even on AC power #gnome	140	5.3k	18d
System Suspends #f38	2	973	Sep 16
How does one set Fedora 38 gnome to never suspend processing? #gnome #f38	3	165	Oct 23
Fedora 38 Silverblue suspends even though Power settings disallow it #gnome #f38 #silverblue	3	658	Sep 1
Can Fedora Workstation be configured so SSH logins inhibit suspend? #gnome #workstation	8	1.1k	Jun 27